

You can access the manuals in our Help Center:
<https://help-noddprint-pt.scrollhelp.site>

Download

- 1 Log in to the NDD Print 360 Resources Portal <https://resources.noddprint.com/downloads> with your credentials.
- 2 Download NDD Print Host, NDD Print Releaser and NDD Print MF HP modules.

NOTE
 To receive your credentials, you should request through Support of NDD Tech <https://ndd.tech/ndd-print/suporte/>


Pre-requirements

Confirm the following requirements:

HARDWARE (MINIMUM)	OPERATING SYSTEM	SOFTWARE	PORTS
Processor: Dual-Core 1.7GH	Windows Server 2008 Standard Edition (32 Bits) com SP2	Net framework 4.8	NDD TCP – 5656, 56562, 56563, 56569, 56570
Memory: 4GB	Windows Server 2008 Standard Edition R2 (64 Bits) com SP1		Environment TCP – 443, 80, 389, 686 UDP – 161 e 162
Disk Space: More than 10 GB	Windows Server 2012 – 2016 – 2019 Standard Edition (64 Bits)		

1 Installation


NDD Print Host



NOTE
 During the installation, the software will test the connection with the NDD Print Data Center, which will be performed through the HTTPS Protocol (Port 443). In some cases, it will be necessary to configure the Proxy to allow the connection. When required, the installer will pop-up a message, then you need to click 'Accept' to start the Proxy setup assistant.

This module allows to use a SQL Server Database to improve performance, recommended when the environment has more than 200 printers.

NDD Print Releaser



NOTE
 NDD Print Agent is installed with NDD Print 360 Releaser.

If the NDD Print 360 Releaser is installed on another server than the NDD Print Host, you will be prompted for the Server Address at installation time. For more information about other installation methods, check the manual.

This module allows to use a SQL Server Database to improve performance, recommended when the environment has more than 200 printers.

NDD Print MF HP



NOTE
 The installation language will be in accordance with the NDD Print Host.




If the NDD Print MF HP is installed on another server than the NDD Print Host, you will be prompted for the Server Address at installation time. For more information about other installation methods, check the manual.

2 Basic configuration





NDD Print Host

Integration with AD





Configure the integration to enable LDAP sync and authentication

- 1 On the Users tab

- 2 Click Domain Integration

- 3 Click Add
- 4 On Connection fill in the fields according to the domain configuration

- 5 Click Add



Enable authentication

- 1 On the Users tab

- 2 Click Domain Integration

- 3 Click Properties
- 4 Integrated Authentication

- 5 Select the Enable checkbox

- 6 Click Apply
- 7 Click OK



Enable sync

- 1 On the Users tab

- 2 Click Domain Integration

- 3 Click Properties
- 4 Select General settings

- 5 Choose the Objects (users, groups and/or accounts) that will be synchronized


Select User attributes that will be synchronized





- 1 Select Users

- 2 Choose the Attributes


Select Account attributes to be synchronized

- 1 Select Accounts

- 2 Choose the Attributes


Authentication Method and Default Domain

Allows you to configure the way users authenticate on the NDD Print Client HP

- 1 On the Users tab

- 2 In General Tab Click Set Authentication

- 3 Select Authentication Method

- 4 Select Default Domain

- 5 Click OK


NOTE
For more information about LDAP Sync, check the manual.

NDD Print Releaser

Default domain




Select the domain that will be used to identify the retained print jobs

- 1 Click Tools
- 2 Select Settings
- 3 Identification Tab
- 4 Select Integrated Domain
- 5 Choose Domain
- 6 Select Use select domain for all printed documents



Create a Print Group (virtual queue)

Create a Print Group, which will be used for the users to be able to submit the documents for retention.

- 1 Click Print Groups

- 2 Click Add

- 3 Fill in the Group Name
- 4 Click Next
- 5 Select Driver

- 6 Click Finish

NOTE
If you don't have a driver installed, use the Add button.

NOTE
If you don't have a driver installed, use the Add button.

NDD Print Agent


Job Accounting

The NDD Print Agent automatically identifies all print queues that are installed locally and enables them for job accounting

NDD Print MF HP

Default domain and print job types

Configure the types of print jobs and the Default Domain for identification for the job accounting.




NOTE

For more information about NDD Print 360 Job Accounting, check the manual:

3 Adding Printer

NDD Print Host

Add printers to search for page counts, print supplies, and events.




NOTE

To perform the batch import, check the manual.


NDD Print Releaser

Add a printer that will be used as an Output Queue in Secure Print Release



Add a printer to the Group (virtual queue)

Add a printer to the Print Group to release retained print jobs.




NOTE

If the printer queue is not created, use the option Add to create a Printer Queue.

NDD Print MF HP

Add a printer to use Job Accounting, Secure Print Release, and Print Policy Management features.



NOTE

For more information about Adding Printers, check the manual